

Steps To Run The Chiller Machine Python Utility


1. Keep the Chiller Machine Automation python utility package at your desired location in your system. For example keep this package at "C:\Chiller Machine Automation" location.



2. Open the "Input" folder of your utility package and make sure that your input excel template (i.e Efficiency Data.xlsx) is available here.




3. Open command prompt (Press Window + R keys) and Press "OK".



4. Go to your python utility path (i.e. C:\Chiller_Machine_Automation) by executing the following command from the command prompt.


Command: cd <your python utility package path>



5. Run the following command from the command prompt. Command: python main.py



6. Make sure that you will get the "Execution Started" print on your command prompt.





7. Once execution is started successfully, users will get the pop-up windows with the chiller machine parameters.




8. Users need to select all the appropriate COM PORTs from the drop down list for each required chiller machine parameters.


Chiller Machine Efficiency	- a x
Chiller Efficiency (KW/TR)	*** This is your Log Window ***
COP	Usage: Please select all the port number and fill up timing and counting paramet er then press START button
Chiller Approch (Deg C)	
Condensor Approch (Deg C)	
INPUTS	
Parameters Unit Port No. Value Chilled Water Flow m*3/hr Chiller Power Kw Ambient Dry Buld Temp. (DBT) Deg C Ambient Wet Buld Temp. (WBT) Deg C Relative Humiding (RBH) %	
CHILLED WATER PARAMETERS Parameters Unit Port No. Value Chilled Water Temp. Indet (Tc out) Deg C Chilled Water Temp. Outlet (Tc out) Deg C	
COOLING WATER PARAMETERS	
Parameters Unit Port No. Value Cooling Water Temp. Inlet (Tcw in) Deg C Cooling Water Temp. Outlet (Tcw out) Deg C Refrigerent Temp. in Condensor Deg C OUTPUTS	
Parameters Unit Value Chiller Range Deg C C Condensor Range Deg C C Chiller Operating TR TR TR Chiller Power Kw F	
Timer (Minutes) Counter (Numbers)	
Start Stop	





9. Users need to fill up Timer (Minutes) and Counter (Numbers) parameters.







10. Press the "Start" button to start the utility




11. Now, python utility is started and user will getting the Measurement - # print on Log Window




12. This python utility automatically reads the appropriate COM PORT and reflects the value to appropriate parameters.




13. Based on the received value of Inputs, Chilled Water and Cooling water parameter values, this utility automatically calculates the Output parameters, Chiller Approach, Condenser Approach, COP and Chiller efficiency parameters.



14. Wait until measurement reaches Counter parameter value.




15. User can stop the utility and get the efficiency data by pressing the Stop button




16. Execution will stop once the user presse Stop button and receives the "END" print on command prompt.



17. Open the "Output" folder of your Chiller Machine python utility package to get your efficiency data and best efficiency data.



18. To get all the efficiency data with each and every parameters value, please open "Efficiency_Result.xlsx" file



19. To get the best efficiency value and related parameters value, please open "Best Efficiency Data.txt" file

```
Best_Efficiency_Data - Notepad
```

File Edit Format View Help

```
_____
Best Efficiency = 0.0684542152387064 (KW/TR)
______
Sr. No.
                                            :21
Chilled Water Flow - (m^3/hr)
                                            :29456.0
Chiller Power - (Kw)
                                            :29349.0
Ambient Dry Build Temp.(DBT) - (Deg C)
                                            :29598.0
Ambient Wet Build Temp.(WBT) - (Deg C)
                                            :28052.0
Relative Humidity (RH) - (%)
                                            :29747.0
Chilled Water Temp. Inlet (Tc in) - (Deg C)
                                            :18072.0
Chilled Water Temp. Outlet (Tc out) - (Deg C)
                                            :18028.0
Refrigerent Temp. in Chiller (Deg C)
                                            :8751.0
Cooling Water Temp. Inlet (Tcw in) - (Deg C)
                                            :8477.0
Cooling Water Temp. Outlet (Tc out) - (Deg C)
                                           :8115.0
Chiller Range - (Deg C)
                                            :44.0
Condensor Range - (Deg C)
                                            :-362.0
Chiller Operating TR - (TR)
                                            :428739.1199746755
COP
                                            :51.37740587246358
Chiller Approch - (Deg C)
                                            :-1482.0
Condensor Approch - (Deg C)
                                            :636.0
```